

Royal Exclusiv pumps & skimmers

Royal Exclusiv Aquarien-Anlagenbau Christian Walter GmbH & Co. KG
Vorgebirgsstr. 28 // 50389 Wesseling // Germany

Fon +49(0)2236/88055-0 // Fax +49(0)2236/88055-20
info@royal-exclusiv.de // www.royal-exclusiv.de



Since 1986



User guide for network-configuration Red Dragon® 4 pumps VS22

For all Red Dragon® 4 Dreamliner and Superflow pumps 480 - 1550 Watt

v3.0

ENG

XP | Win7 | MAC




Connection of the RD4 pump using Windows XP



Step 1: Open “Windows Start Menu” and do a right click on “Network environment”. Select “Properties”.


Step 2: Navigate to “LAN Connection” and open a navigation bar by right clicking. Select „Properties”.



For more information, please visit www.royal-exclusiv.de. Simply enter the part number or name into the search box or email: info@royal-exclusiv.de.

All information subject to change. We try our best, but printing errors reserved.


Step 3: Navigate to “Internet Protocol (TCP/IP)” and click on “Properties”.



Step 4: Tick “Use the following IP address” and type in the following data:

IP address: 192. 168. 0. 201 **Subnet mask:** 255. 255. 255. 0

Confirm your settings by clicking “OK”.



Step 5:

Plug the **Ethernet cable** of the pump into the PC input.




Connect plug of pump to the socket.

If you connected these both small steps rightly, the **blue LED light** of the pump is blinking. This is the sign for Stand-By



Step 6: Open your web browser (Internet explorer/ Mozilla / Safari) and type in the following URL: <http://192.168.0.245> (or: <http://192.168.0.245/index.htm>). After you typed in the URL confirm with **enter key**.



For more information, please visit www.royal-exclusiv.de. Simply enter the part number or name into the search box or email: info@royal-exclusiv.de.

All information subject to change. We try our best, but printing errors reserved.




Since 1986



Connection of the RD4 pump using Windows Vista / Windows 7


Win7




Step 1:

Choose “Control Panel” from the “Windows Start Menu”.

Step 2: Select “Network Center” at the control panel.



Please note: If you're not able to see the screen below, another setting at your computer is configured. To change the view click on the top right corner “Display” and select “Small Symbols”.




For more information, please visit www.royal-exclusiv.de. Simply enter the part number or name into the search box or email: info@royal-exclusiv.de.


All information subject to change. We try our best, but printing errors reserved.

Step 3: Click on "View status".


Network and Sharing Center



Step 4: Click on „Properties“.




Step 5: Select „Internet Protocol Version 4 (TCP/IPv4)“ and click on “Properties”.



Step 6: Tick „Use the following IP address“ and type in the following data:

IP address: 192. 168. 0. 201 **Subnet mask:** 255. 255. 255. 0

Confirm your settings by clicking “OK”.






Since 1986



Win7

Step 7:

Plug the **Ethernet cable** of the pump into the PC input.




Connect plug of pump to the socket.

If you connected these both small steps rightly, the **blue LED light** of the pump is blinking. This is the sign for Stand-By



Step 8: Open your web browser (Internet explorer/ Mozilla / Safari) and type in the following URL: <http://192.168.0.245> (or: <http://192.168.0.245/index.htm>). After you typed in the URL confirm with **enter key**.



For more information, please visit www.royal-exclusiv.de. Simply enter the part number or name into the search box or email: info@royal-exclusiv.de.

All information subject to change. We try our best, but printing errors reserved.

Connection of the RD4 pump using MAC (Apple)

Step 1: Open your web browser (Safari) and **deselect Wi-Fi connection.**



Step 2:

Plug the **Ethernet cable** of the pump into the PC input.



Connect plug of pump to the socket.

If you connected these both small steps rightly, the **blue LED light** of the pump is blinking. This is the sign for Stand-By





Since 1986





MAC

Win7

XP

Step 3: Open your web browser (Internet explorer/ Mozilla / Safari) and type in the following URL:
<http://192.168.0.245> (or: <http://192.168.0.245/index.htm>). After you typed in the URL confirm with enter key.



Overview

After successful connection of the pump to your network, you will see the menu item „Overview“
All relevant applications for your pump can be viewed here.

For more information, please visit www.royal-exclusiv.de. Simply enter the part number or name into the search box or email: info@royal-exclusiv.de.

All information subject to change. We try our best, but printing errors reserved.

Royal Exclusiv pumps & skimmers

Royal Exclusiv Aquarien-Anlagenbau Christian Walter GmbH & Co. KG
Vorgebirgsstr. 28 // 50389 Wesseling // Germany




Fon +49(0)2236/88055-0 // Fax +49(0)2236/88055-20
info@royal-exclusiv.de // www.royal-exclusiv.de



MAC

Win7

XP



Pump

Under the menu item „Pump“ 5 different modes of the pump configuration can be set. Furthermore, the revolutions and pressure options can be set here.

For more information, please visit www.royal-exclusiv.de. Simply enter the part number or name into the search box or email: info@royal-exclusiv.de.

All information subject to change. We try our best, but printing errors reserved.

Royal Exclusiv pumps & skimmers

Royal Exclusiv Aquarien-Anlagenbau Christian Walter GmbH & Co. KG
Vorgebirgsstr. 28 // 50389 Wesseling // Germany




Fon +49(0)2236/88055-0 // Fax +49(0)2236/88055-20
info@royal-exclusiv.de // www.royal-exclusiv.de



MAC

Win7

XP



Network

Network information can be set and viewed here. In case of changes, please note the dates.

Log

Additional information or possible errors / hints

For more information, please visit www.royal-exclusiv.de. Simply enter the part number or name into the search box or email: info@royal-exclusiv.de.

All information subject to change. We try our best, but printing errors reserved.